

Timezone

By default, Batocera is configured for Central European Time (CET) timezone.

In Batocera **v31** and higher, you can select your own timezone from the menu **SYSTEM SETTINGS** → **TIMEZONE**. From the same menu, you can also toggle the clock to 12-hour format if desired.

Older versions of Batocera

To adapt to your local time zone, you need to edit `/userdata/system/batocera.conf` and add/modify a line with:

```
system.timezone=America/Los_Angeles
```

To list all the group names of the available timezone, [from SSH/terminal](#) run:

```
# ls /usr/share/zoneinfo/
```

This command returns several directories (each one being a group of time zones). In each of these directories are more directories that contain the actual timezones. For example, to see all the available options for `Los_Angeles`, run the following:

```
# ls /usr/share/zoneinfo/America/
```

These instructions are still valid for Batocera **v31** and higher, if you need to change them manually.

Troubleshooting

Batocera keeps resetting my clock whenever I boot back into Windows!

This is not actually Batocera, [Windows will just overwrite the RTC value with the localized time](#), whereas Batocera uses the more globally accepted UTC time. If you'd rather not mess with Windows' registry at all, you can just tell Windows not to update the time via the Internet time. Right-click the time on your taskbar to get into its properties to change this. However, this will mean the time displayed on your Windows machine will not be correct. If you'd like correct time on both operating systems, read the following sections:

Fix this in Windows manually

The fix for this on Windows (summarized from the [Arch wiki's page about it](#)):

1. Hit [Winkey]+[R] and run "regedit". Confirm administrator privileges
2. Make a backup by going to **File** → **Export...**
3. Navigate to

HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Control\TimeZoneInformation\

4. Add a DWORD value with hexadecimal value 1 named RealTimeIsUniversal



For 64-bit versions of Windows 7 and older builds of Windows 10, there was a bug that made it necessary to have a QWORD value with hexadecimal value of 1.

5. Yeehaw, you're done. Windows might ask to update the clock, let it do so

Fix this in Windows automatically

You can also just download and install/import this reg file (if you trust strangers on the internet):

[UTCtimefix.reg](#)

```
Windows Registry Editor Version 5.00
```

```
[HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Control\TimeZoneInformation]
```

```
"RealTimeIsUniversal"=dword:00000001
```

Just double-click the file, or go to Regedit's **File** → **Import...** menu. It is strongly recommended to only use this on the later versions of Windows 10.

Changing Batocera to use Windows' local time instead

You can use a custom script in Batocera **v32** and up to tell it to use the local time just like Windows does instead.

Put the following file into `/boot/boot-custom.sh`:

[boot-custom.sh](#)

```
#!/bin/bash
```

```
hwclock --systz --localtime
```

From:

<https://www.wiki.batocera.org/> - **Batocera.linux** - Wiki

Permanent link:

<https://www.wiki.batocera.org/timezone>

Last update: **2022/06/12 08:37**



